

Lesson 1 Edit Action with PC Software

1. Purpose


Program an action to make MaxArm suck the block and place it to the side.

This lesson aims to help you master how to program action. If want to refer to the standard action, please view the provided action group file in folder “Appendix/3.MaxArm Action Group File”.


2. Action Realization

2.1 Action Design

1) Turn on MaxArm and connect it to computer with USB cable. Then open PC software.



2) Click “Reset” to make MaxArm return to the initial posture.




3) Change the running time to “500” ms, and click “Add action” to add the

initial posture of robotic arm as the first action.



Index	Duration(ms)	X	Y	Z	Nozzle angle	Nozzle status
1	500	0	-163	212	0	0

4) Click “Z-” in end coordinate control area to get MaxArm lower to above the block.



Place the mouse cursor over “Z-” button and hold down the left button to lower MaxArm quickly. Click to make fine adjustments.

5) Set the running time to 800ms and click “Add action” to add current action to action data list.

	2	800	0	-163	100	0	0
--	---	-----	---	------	-----	---	---

6) Set the running time to 800ms and click “Z-” to lower MaxArm to the top of block. Then click “Add action”.

	3	800	-8	-171	88	0	0
--	---	-----	----	------	----	---	---

7) Click “Suck” in nozzle suction control area and set the running time to 500ms. Then click “Add action”.



	4	500	-8	-171	88	0	1
--	---	-----	----	------	----	---	---

8) After sucking the block, click “Z+” to lift MaxArm and set the running time to 800ms. Then click “Add action”.

	5	800	-8	-171	152	0	1
--	---	-----	----	------	-----	---	---

9) Adjust the value of x and y axes to make MaxArm turn to the left. Set the running time to 1500ms and click “Add action”.

	6	1500	152	-11	152	0	1
--	---	------	-----	-----	-----	---	---

10) Adjust the value of z-axis to lower MaxArm. Set the running time to 800ms and click “Add action”.

	7	800	152	-11	96	0	1
--	---	-----	-----	-----	----	---	---

11) Add a transition action. Set the running time to 200ms and click “Add action”.

	8	200	152	-11	96	0	1
--	---	-----	-----	-----	----	---	---

12) Click “Release” in suction nozzle control area to put down the block.



13) Set the running time to 500ms and click “Add action”.

	9	500	152	-11	96	0	0
--	---	-----	-----	-----	----	---	---

14) Click “Z+” to lift MaxArm. Set the running time to 800ms and click “Add action”.

	10	800	152	-11	184	0	0
--	----	-----	-----	-----	-----	---	---

15) Click “Reset” and set the initial posture as the ending action. Then set the running time to 1200ms and click “Add action”.


▶	11	1200	0	-163	212	0	0
---	----	------	---	------	-----	---	---

16) The following table are the complete data of action group. If want to adjust an individual action, you can directly double click the corresponding parameters to modify.

	Index	Duration(ms)	X	Y	Z	Nozzle angle	Nozzle status
▶	1	500	0	-163	212	0	0
	2	800	0	-163	100	0	0
	3	800	-8	-171	88	0	0
	4	500	-8	-171	88	0	1
	5	800	-8	-171	152	0	1
	6	1500	152	-11	152	0	1
	7	800	152	-11	96	0	1
	8	200	152	-11	96	0	1
	9	500	152	-11	96	0	0
	10	800	152	-11	184	0	0
	11	1200	0	-163	212	0	0


2.2 Run Action Group

After action programming , click on running icon, as shown in the image below, to check the running effect of action group.



2.3 Save and Download Action

1) Click “Save action file” to save the action file for later debugging. Here the action group file is named with “20”.



2) After saving the action file, download action group to the corresponding action group number. Select “20” in action group selection box and click “Download”.



After downloading, the prompt “Action group is downloaded” will pop up.
